## **Laboratory Quick Guide**


### **Antigen Detection ELISA**


#### **Student Workstation Checklist**

One workstation serves 4 students.

Item (Label)	Contents	Number	(✔)
Yellow tubes	Student test samples (0.25 ml)	4	
Violet tube (+)	Positive control (0.5 ml)	1	
Blue tube (–)	Negative control (0.5 ml)	1	
Green tube (PA)	Primary antibody (1.5 ml)	1	
Orange tube (SA)	Secondary antibody (1.5 ml)	1	
Brown tube (SUB)	Enzyme substrate (1.5 ml)	1	
12-well microplate strips		2	
50 μl fixed-volume micropipet or		1	
20–200 µl adjustable micropipet			
Yellow tips		10–20	
Disposable plastic transfer pipet		1	
70–80 ml wash buffer in beaker	Phosphate buffered saline	1	
	with 0.05% Tween 20		
Large stack of paper towels		2	
Black marking pen		1	


- 1. Label the yellow tubes with each student's initials.
- Label your 12-well strip. On each strip label
  the first 3 wells with a "+" for the positive
  controls and the next 3 wells with a "-" for
  the negative controls. Label the remaining
  wells with your and your partner's initials
  (3 wells each).
- 3. Use a <u>fresh</u> pipet tip to transfer 50 µl of the positive control (+) into the three "+" wells.
- 4. Use a <u>fresh</u> pipet tip to transfer 50 μl of the negative control (–) into the three "–" wells.
- 5. Transfer 50 μl of each of your team's samples into the appropriately initialed three wells, using a <u>fresh</u> pipet tip for each sample.
- 6. Wait 5 minutes while the proteins in the samples bind to the plastic wells.






#### 7. WASH:

- Tip the microplate strip upside down onto the paper towels, and gently tap the strip a few times upside down. Make sure to avoid splashing samples back into wells.
- b. Discard the top paper towel.
- c. Use your transfer pipet to fill each well with wash buffer, taking care not to spill over into neighboring wells. Note: the same transfer pipet is used for all washing steps.
- d. Tip the microplate strip upside down onto the paper towels and tap.
- e. Discard the top 2-3 paper towels.




- 8. Repeat wash step 7.
- Use a <u>fresh</u> pipet tip to transfer 50 μl of primary antibody (PA) into all 12 wells of the microplate strip.
- 10. Wait 5 minutes for the antibodies to bind to their targets.
- Wash the unbound primary antibody out of the wells by repeating all of wash step 6 two times.
- 12. Use a <u>fresh</u> pipet tip to transfer 50 μl of secondary antibody (SA) into all 12 wells of the microplate strip.

# **WASH**




### WASH 2x



- 13. Wait 5 minutes for the antibodies to bind to their targets.
- 14. Wash the unbound secondary antibody out of the wells by repeating wash step 6 **three** times.

# WASH 3x

15. Use a <u>fresh</u> pipet tip to transfer 50 μl of enzyme substrate (SUB) into all 12 wells of the microplate strip.



16. Wait 5 minutes. Observe and record the results.





Bio-Rad Laboratories, Inc.

Life Science Group Web site www.bio-rad.com USA (800) 4BIORAD Australia 02 9914 2800 Austria (01)-877 89 01 Belgium 09-385 55 11 Brazil 55 21 2527 3454 Canada (905) 712-2771 China (86 21) 6426 0808 Czech Republic + 420 2 41 43 05 32 Denmark 44 52 10 00 Finland 09 804 22 00 France 01 47 95 69 65 Germany 089 318 84-0 Greece 30 210 777 4396 Hong Kong (852) 2789 3300 Hungary 36 1 455 8800 India (91-124)-2398112/34, 5018111, 6450092/93 Israel 03 951 4127 Italy 39 02 216091 Japan 03-5811-6270 Korea 82-2-3473-4460 Latin America 305-894-5950 Mexico 55-52-00-05-20 The Netherlands 0318-540666 New Zealand 64 94 15 2280 Norway 23 38 41 30 Poland + 48 22 331 99 99 Portugal 351-21-472-7700 Russia 7 095 721 1404 Singapore 65-64153188 South Africa 00 27 11 4428508 Spain 34 91 590 52 00 Sweden 08 555 12700 Switzerland 061 717 95 55 Talwan (886 2) 2578 7189/2578 7241 United Kingdom 020 8328 2000

Bulletin 3135 US/EG Rev B 05-0469 0505 Sig 1204